


Z1K_ACTUAL - Upload of Actual statistical key figures - PF1

STEP 1

Enter transaction Z1K_ACTUAL in the transaction field of main menu.

Click on the line Z1K_UPLOAD_RATIOS and then in EXEC

PROGRAM



CO MENU for EXCEL FILE upload

INFO for PROGRAM | EXEC PROGRAM | Download Example

Menu of the program to UPLOAD ACTUAL postings

```
XXXX XXX XXXX X X XXXX X
X X X X X X X X X
XXXX X X X XXXX X
X X XXX X XXXX X X XXXX
```

Click on a line to select the program and choose a function (icon on top of page):

- to display the program documentation
- to run the program
- to download an example of the EXCEL file
- a window asks you for a file name and creates an excel file on your PC then you can open the file to see the example

Z1K_ULKB21	Upload Activity Type posting on Ctr/WBS/Order/Network
Z1K_ULKB21_DE	Upload Activity Type posting on Ctr/WBS/Order/Operation/Network
Z1K_UPLOAD_RATIOS	Upload ACTUAL Statistical Ratio Postings (KB31)
Z1K_ULKB11	Upload ACTUAL Reposting (KB11)
Z1K_ULKB11_ORDER	Upload ACTUAL Reposting (KB11) SENDER=ORDER

STEP 2

Enter a document date and define the following fields:

- **File:** X=EXCEL; A=ASCII; U=UNIX: X for Excel format;

- **Controlling Area:** CHEF;

- **Transaction Screen VARIANT:** SAP05;

- **Document date/Posting Date:** Period for the Key figure upload (if the period is not defined an error message appears not allowing the passage to the next screen) ;

- **BTCI User:** Personal User code (defined by default);

- **BTCI Name:** Batch Input Name reference: CO_KB31_CCode;

- **BTCI Keep ?:** X (for batch session caption in SM35);

Press Execute



CO Upload Statistical Ratios

File: X=EXCEL; A=ASCII; U=UNIX ☒

Controlling Area

Transaction Screen VARIANT

Document date

Posting Date

BTCI User

BTCI Name

BTCI Keep ? ☒

PC File NAME



Upload file

After execution a message box requiring the upload file will be displayed.

STEP 3

The program generates a batch input session for transaction KB31N.

Go to transaction SM35;

Select the session and process it;

Statistical key figures are posted.

Batch Input: Log Overview

Display | Analyze session

Log information

Session QueueID: 06020914310752180038 Sess.name: CO_KB31_JOKL
Created on: 09.02.2006 Created by: DE02468

Log Overview

Date	Time	Sess.name	Session status	User	Queue ID	Appl. server
09.02.2006	14:38:33	CO_KB31_XXXX	Processed	DE02468	06020914310752180038	srf1sapr3

 Log

Log attributes			
Name	CO_KB31_XXXX	Queue ID	06026914310752180038
Created on	09.02.2006	TermSe ID	BDC16075218003818421
		☐ Details	
Time	Message	Transac.	
14:38:33	Session CO_KB31_XXXX is being processed by user DE02468 in mode...		
14:38:35	Document is posted under numbr 400035602	KB31	
14:38:35	Transaction was processed successfully	KB31	
14:38:36	Processing statistics		
14:38:36	1 transactions read		
14:38:36	1 transactions processed		
14:38:36	0 transactions with errors		
14:38:36	0 transactions deleted		
14:38:36	Batch input processing ended		

Run transaction KB33N and enter the document number previously collected;

You can also check CO objects receivers using report ZE04 running transaction GR55.

The screenshot shows the SAP Fiori 'Indicatori statistici' application. The top navigation bar includes the SAP logo and several icons. The main header area displays the title 'Vie, indicatori statistici'. Below the header, there is a filter bar with the following fields: 'Data da: 24.11.2018', 'Data fino: 24.11.2018', and 'Periodo: 11'. The main content area contains a table of statistical indicators. The table has columns: 'Indicatore', 'Codice desc.', 'Codice desc.', 'Indicatore', 'Valore', 'Unità di misura', and 'Trend'. The data rows show various indicators with their respective values and trends.

Indicatore	Codice desc.	Codice desc.	Indicatore	Valore	Unità di misura	Trend
Indicatore di performance	00000000	00000000	Indicatore di performance	14.897.195	00000000	00000000
Indicatore di qualità	00000000	00000000	Indicatore di qualità	7.585.296	00000000	00000000
Indicatore di sicurezza	00000000	00000000	Indicatore di sicurezza	2.754.750	00000000	00000000
Indicatore di sostenibilità	00000000	00000000	Indicatore di sostenibilità	6.287.236	00000000	00000000
Indicatore di innovazione	00000000	00000000	Indicatore di innovazione	6.286.236	00000000	00000000
Indicatore di efficienza	00000000	00000000	Indicatore di efficienza	3.889.236	00000000	00000000
Indicatore di produttività	00000000	00000000	Indicatore di produttività	53.731.383	00000000	00000000
Indicatore di competitività	00000000	00000000	Indicatore di competitività	2.842.800	00000000	00000000
Indicatore di redditività	00000000	00000000	Indicatore di redditività	3.887.750	00000000	00000000
Indicatore di crescita	00000000	00000000	Indicatore di crescita	24.199.716	00000000	00000000
Indicatore di sviluppo	00000000	00000000	Indicatore di sviluppo	6.485.400	00000000	00000000
Indicatore di trasformazione	00000000	00000000	Indicatore di trasformazione	3.246.116	00000000	00000000
Indicatore di impatto	00000000	00000000	Indicatore di impatto	5.446.116	00000000	00000000