

PPE - Reload one(more) month(s)

Steps to Load RCS Data manually in PPE

Step 1

Create a backup copy of "GL_GMARGIN" table

```
create table gl_gmargin_250418 as
select * from gl_gmargin;
```

Step 2

Pull the RCS file from the RCS system and store it in BI4 in the path "exploit/arrive/tmp"

```
isis@solax025:/home/isis > su exploit
exploit's Password:
isis@solax025:/home/isis > eval $(ICleEnvService Premier_Economique@DW2_APP)
isis@solax025:/home/isis > cd /exploit/arrivee/tmp
isis@solax025:/exploit/arrivee/tmp > sftp wp1app07.ibm.be.solvay.com
exploit@wp1app07.ibm.be.solvay.com's password:
Connected to wp1app07.ibm.be.solvay.com.
sftp> cd /exploit/FA/data or /exploit/FA/archive
sftp> ls -ltr
```

Step 3



Modify the files (**Rename** the RCS files pulled in the "exploit/arrive/tmp by adding ".txt")

As the files which are pulled from RCS does not have an extension ,

the file cannot be loaded through sql loader Without extension .

so we need to add an extension to the files.

Example

 W158001_ZVE1R.txt	305,424	Text Do...	4/24/2018 7:24:00 PM
 W158001_ZVE1R	305,424	File	4/24/2018 9:25:00 PM

From the above example the highlighted one is the once we receive from RCS system,

And the one which is un marked is the modified one.

Step 4

, Start the load the integrate data:

Login UX4 and set up Environment :

Login isis

su exploit

```
eval $(ICleEnvService Premier_Economique@DEV3_APP)
```

*** in UNX7 the parameter will be different ****

```

To set up PPE environment, execute the following command :
eval $(ICleEnvService Premier_Economique@DEV3_APP)

To set up SAFIR environment, execute the following command :
eval $(ICleEnvService SAFIR@SAFIR_APP)

To set up PPS environment, execute the following command :
eval $(ICleEnvService Premier_Pilotage@PER_APP)

To set up I_CARE environment, execute the following command :
eval $(ICleEnvService I-CARE@ICR_APP)

To set up ECO_VMI environment, execute the following command :
eval $(ICleEnvService ECO_VMI@ECOVMI_APP)

To set up MSDS environment, execute the following command :
eval $(ICleEnvService MSDS@MSDS_APP)

To set up RAP environment, execute the following command :
eval $(ICleEnvService RAP@RAP_APP)

Pour acceder a l'environnement du I-SIS Agent, tapez la commande:
. /home/isis/Agent/profile.Agent

isis@solax005:/home/isis > su exploit
exploit's Password:
isis@solax005:/home/isis > eval $(ICleEnvService Premier_Economique@DEV3_APP)
isis@solax005:/home/isis >
isis@solax005:/home/isis >
isis@solax005:/home/isis >

```

```

isis@solax005:/exploit/arrivee/tmp > cd /exploit/arrivee/tmp

```

Run the below loader scripts one by one to load all the files

```

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_3865.txt log=./load_W158001_3865.log bad=
/bad_W158001_3865.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_3944.txt log=./load_W158001_3944.log bad=
/bad_W158001_3944.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6059.txt log=./load_W158001_6059.log bad=
/bad_W158001_6059.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6062.txt log=./load_W158001_6062.log bad=
/bad_W158001_6062.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6068.txt log=./load_W158001_6068.log bad=
/bad_W158001_6068.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6110.txt log=./load_W158001_6110.log bad=
/bad_W158001_6110.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6111.txt log=./load_W158001_6111.log bad=
/bad_W158001_6111.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6268.txt log=./load_W158001_6268.log bad=
/bad_W158001_6268.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6297.txt log=./load_W158001_6297.log bad=
/bad_W158001_6297.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6301.txt log=./load_W158001_6301.log bad=
/bad_W158001_6301.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6322.txt log=./load_W158001_6322.log bad=
/bad_W158001_6322.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6346.txt log=./load_W158001_6346.log bad=
/bad_W158001_6346.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6348.txt log=./load_W158001_6348.log bad=
/bad_W158001_6348.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6526.txt log=./load_W158001_6526.log bad=
/bad_W158001_6526.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6577.txt log=./load_W158001_6577.log bad=
/bad_W158001_6577.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6746.txt log=./load_W158001_6746.log bad=
/bad_W158001_6746.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_6811.txt log=./load_W158001_6811.log bad=
/bad_W158001_6811.log

```


sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_7788.txt log=./load_W158001_7788.log bad=.
/bad_W158001_7788.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_7794.txt log=./load_W158001_7794.log bad=.
/bad_W158001_7794.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_7797.txt log=./load_W158001_7797.log bad=.
/bad_W158001_7797.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_7810.txt log=./load_W158001_7810.log bad=.
/bad_W158001_7810.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_7811.txt log=./load_W158001_7811.log bad=.
/bad_W158001_7811.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_7988.txt log=./load_W158001_7988.log bad=.
/bad_W158001_7988.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_8090.txt log=./load_W158001_8090.log bad=.
/bad_W158001_8090.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_8485.txt log=./load_W158001_8485.log bad=.
/bad_W158001_8485.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_ZBR1.txt log=./load_W158001_ZBR1.log bad=.
/bad_W158001_ZBR1.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_ZFR3.txt log=./load_W158001_ZFR3.log bad=.
/bad_W158001_ZFR3.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_ZFR9.txt log=./load_W158001_ZFR9.log bad=.
/bad_W158001_ZFR9.log

sqlldr pe_dc/pe control=/home/isis/ICles/PR_ECO/V1/INTEGRATION/ctl/gl_gmargin.ctl data=./W158001_ZVE1.txt log=./load_W158001_ZVE1.log bad=.
/bad_W158001_ZVE1.log

Step 6

Run "GL_GMARGIN.PL/SQL" script in sql developer or TOAD

Step 7

Run "PURGE_RECYCLAGE_P2" in sql developer or TOAD after "GL_GMARGIN.PL/SQL" script is completed

-