

# How to update the Energy Efficiency Conversion rate

## The flat file

### Check the new file

Jean-Louis Tartarin sends a request to the Support Team (RHD-RCS SUPPORT BW) to update the energy efficiency conversion rate with the new file.

Then, the support team has to check the new file:

- The title : "DSO\_UTCT.csv"
- The format has to be like that :
  - 1<sup>st</sup> column: C\_UTILITY
  - 2<sup>nd</sup> column: UNIT
  - 3<sup>rd</sup> column: K\_TXCVUT (be careful, the separation is " " **And not** " ")


	A	B	C
1	C_UTILITY	UNIT	K_TXCVUT
2	COND	M3	0.100
3	CONDSP	BZ	0.293
4	CONDSP	M3	0.083
5	DOWTHE	KTH	0.001161111
6	ELEC	KWH	0.001
7	FUEL	TO	11.070
8	GAS	BZ	0.293
9	GAS	KWH	0.001
10	GAS	KN3	11.300
11	GAS	NM3	0.010
12	GASR	M3	0.010
13	GASSP	BZ	0.293
14	GAZ	KN3	11.300
15	GNTHER	KN3	11.300

### Import the new file


When the new file is checked, the support team can add this one in the BW server.




- Open FileZilla Client :
- Connect to WBP : put "FRPARWBP" in the first cell and click on "Connexion"




- Go to the folder "/BW/Value Stream"




- Rename the last version of the file "DSO\_UTCT.csv", for example "DSO\_UTCT\_oldX.csv" (X is a number) to keep old versions :



- Import the new file : you just have to double click on the file "DSO\_UTCT.csv" in the left part



Then, you have to select "Replace" and validate:



## Update DSO\_UTCT

### Launch Info Package and Data Transfer Process

DSO - Utilities Conversion Rate by Unit	DSO_UTCT	Manage
Transformation: DTS_DSO_UTCT -> DSO_UTCT	06J7Q2V8RCHG2EXXTDLXWYPV1XW...	Change
Conversion Rate for Utilities	DTS_DSO_UTCT	Change DataSources PC_FILE
InfoPackage: Flat File -> DSO_UTCT	ZPAK_4G3540T43T6VJGZ78LJ253GK	Schedule DataSources
Data Transfer Processes	DSO_UTCT	Create Data Tra...
DTP: Flat File -> DSO_UTCT	DTP_4G338NHP0LOTJ0EMZCSRAS8J0	Change
Conversion Rate for Utilities	DTS_DSO_UTCT	Change DataSources PC_FILE
InfoPackage: Flat File -> DSO_UTCT	ZPAK_4G3540T43T6VJGZ78LJ253GK	Schedule DataSources

Active the new data

Contents

Requests

Reconstruction

Requests from DataStore Object:DSO - Utilities Conversion Rate by Unit

Requ...	R...	ID of ...	Req...	Load ...	DTP/InfoPackage	Request D...	Update Date	S
1160687		1160691			DTP: Flat File -> DSO_UTC	05.12.2011	05.12.2011	
1160612		1160626			DTP: Flat File -> DSO_UTC	05.12.2011	05.12.2011	
1133792		1133794			DTP: Flat File -> DSO_UTC	12.11.2011	12.11.2011	