

Display messages in costing run

STEP 1

WP1 + PF1

When there are error  or warning  messages, you must click on  to analyse and clear them

Flow Step	Authorization	Parameter	Execute	Loc	Status	Materials	Errs	Still Open
Selection						1726	26	
Struct. Explosion						1726	26	
Costing						1700	0	0
Analysis								
Marking								
Release								

STEP 2

WP1 + PF1

Click on  to have the list of messages

Message log created on 26.12.2011	
Number of Messages Collected	
Information Messages	1 
Warning Messages	72 
Error Messages	26 
Termination Messages	0 
Total	99 

STEP 3

WP1 + PF1

1 - Type of message

 E Error messages, must be cleared

 W Warning messages, must be analysed and cleared as much as possible

 I Information messages

Costing Run: Selection - Log

Log created on 26.12.2011

Excep...	M...	M...	Plant	Material	St	A...	Message Text
	W	128	7811	32787	1	CK	Material 32787 in plant 7811 has no accounting data
	W			77069	1	CK	Material 77069 in plant 7811 has no accounting data
	W			115117	1	CK	Material 115117 in plant 7811 has no accounting data
	W		7818	49739	1	CK	Material 49739 in plant 7818 has no accounting data
	W		7819	110142	1	CK	Material 110142 in plant 7819 has no accounting data
	I	172	7787	1615996	1	CK	Material 1615996 in plant 7787: No cost est. exists -> ra...
	E	310	7714	68858	1	CK	Material 68858 is marked for deletion
	E			19398	1	CK	Material 19398 is marked for deletion
	E			40928	1	CK	Material 40928 is marked for deletion
	E			50775	1	CK	Material 50775 is marked for deletion
	E			66785	1	CK	Material 66785 is marked for deletion
	E			101132	1	CK	Material 101132 is marked for deletion
	E			101628	1	CK	Material 101628 is marked for deletion
	E			7779	1	CK	Material 66785 is marked for deletion

2 - Message code

3 - Plant code

4 - Material code

5 - Message description

STEP 4

WP1 + PF1

You can double-click on a message to have a more detailed description of the issue

Material 68858 is marked for deletion	
Message no. CK310	
Diagnosis	
Material 68858 was flagged for deletion internally. To delete this deletion flag, you have to change the indicator in the material master record.	
Change material master record	

